
INTRODUCTION TO GIS USING ARCGIS 10.7.1

SESSION 1

Introduction

A GIS (Geographic Information System) is a tool used for computerized mapping and spatial analysis. A GIS provides functionality to capture, store, query, analyze, display and output geographic information.

We will be using ArcGIS 10.7.1, a popular GIS software produced by ESRI. This course is meant to teach some fundamental GIS operations using ArcGIS. It is not meant to be a comprehensive course in GIS or ArcGIS, however, it should get you started using GIS and in position to learn more.



Components of ArcGIS Desktop 10.7.1

ArcMap, ArcCatalog, (and ArcToolbox)

ArcGIS Desktop is comprised of a set of integrated applications, which are accessible from the Start menu of your computer: ArcMap and ArcCatalog.


- ArcMap is the main mapping application which allows you to create maps, query attributes, analyze spatial relationships, and layout final projects.
- ArcCatalog organizes spatial data contained on your computer and various other locations and allows for you to search, preview, and add data to ArcMap as well as manage metadata and set up address locator services (geocoding).
- ArcToolbox is the third application of ArcGIS Desktop. Although it is not accessible from the Start menu, it is easily accessed and used within ArcMap and ArcCatalog. ArcToolbox contains tools for geoprocessing, data conversion, coordinate systems, projections, and more. This workbook will focus on ArcMap and ArcCatalog.

Data Management – ArcCatalog

Searching and Content

Finding and using data is at the center of any GIS project. Let's get started by opening ArcCatalog:

1. Double-click with the left mouse button on the ArcCatalog icon on the desktop, or from the Windows Start menu, select 'Programs' > 'ARCGIS' > 'ArcCatalog' After opening the software, you will see the screen like this one:



The left side of the screen lists a set of possible locations for data in the Catalog Tree. Don't worry if yours does not look exactly the same. It is easy to add directories for data by clicking on

the 'Connect to folder' icon on the top left toolbar. $\stackrel{{\scriptstyle\frown}}{\stackrel{\scriptstyle\leftarrow}{\scriptstyle\leftarrow}}$

Common GIS File Types

KEY WORDS

Geodatabase – The personal geodatabase, or geographic database, file is called the "modern container for GIS data" and is specific to ArcGIS. Geodatabases define, manage, process and store all the types of data that can be used in ArcGIS (i.e., feature, rasters, relationships, measurements, attributes, etc) inside either a Microsoft Access database (.mdb) or a full relational database (SQL Server, Oracle, Informix or DB2).

Shapefiles – ArcGIS shapefile format is a widely adopted standard and comprises three or more associated files. Be careful copying this data to a disk. You must get all of the files associated with a single layer. They will have a variety of file extensions: .shp, .shx, .dbf and sometimes others. If you are copying shapefiles, we recommended that you use the 'File' > 'Data' > 'Export Data' function in ArcMap or through ArcCatalog. This will automatically copy all files associated with a layer. Also, be aware that some of these files may be very large in size.

Layer – According to ESRI, the layer file (.lyr) stores symbology, symbology classifications, labeling properties, scale dependency, and definition. If you save something in this format it means that, unlike shapefiles, colors and other characteristics are saved and will appear the same every time you open it.

Coverages – "A coverage stores a set of thematically associated data considered to be a unit. It usually represents a single layer, such as soils, streams, roads, or land use. In a coverage, features are stored as both primary features (points, arcs, polygons) and secondary features (tics, links, annotation)." Source: ESRI Data Dictionary.

CAD (computer-aided design) – "A computer-based system for the design, drafting, and display of graphical information." Although most commonly used to support engineering, planning, and illustrating activities, these files can be used in a GIS. Source: ESRI Data Dictionary.

Image formats – ArcGIS accepts and uses a variety of image files (.tiff, .jpg, .jp2, .png, etc).

Text files (with x,y coordinates)

Many others...

Term	Definition	Example
View	a collection of themes	Washington, DC
Theme	a single layer of data	Housing
Attribute	a defined characteristic of a theme	Year Built
Value	a specific quality or quantity assigned to an attribute, for a specific instance.	1920

Previewing Data

(

From the catalog tree on the left side, navigate to C:\ESRI\GIS_WRKSHP\. You will see a list of shapefiles. The .shp extension of the file means that these files are in shapefile format and thus can be read by ArcGIS. Although this is not the only file format ArcGIS can read, it is a popular format.

1. To view file extensions, navigate to 'Customize' > 'ArcCatalog Options' > and under the 'General' tab unclick 'Hide file extensions' and hit 'OK'.

ArcCatalog - ArcInfo - C:\GIS_WRKSHP			
ile Edit View Go Geoprocessing Customiz E Edit View A E E E E E E E E E E E E E E E E E E	the second s	noi++i0i#j Ij	
<pre>cMog Tree</pre>	Content: Preview Description	Type Shapefile Shapefile Shapefile Shapefile Shapefile Shapefile Shapefile Shapefile Shapefile Bhapefile BASE Toble BASE Toble Shapefile dBASE Toble	

NOTE: This is what shapefiles look like in Windows Explorer – a combination of 3 to 7 individual files make up one shapefile. You should view GIS data in ArcCatalog.

File Edit View Favorites	Tools	Help		<u></u>
🕝 Back 🔹 🕥 - 🏂	P	Search 😥 Folders 🛄 🔹 🕅	Folder Sync	
ddress 🛅 C:\ESRI\ESRIDATA	A\Maryla	nd		🖌 🄁 Go
-		Name 🔺	Size	Туре 🧹
File and Folder Tasks	۵	Baltimorecity	3 KB	DBF File
😝 Make a new folder		Baltimorecity	1 KB	SHX File
		Baltimorecity.prj	1 KB	PRJ File
Publish this folder to the Web		Baltimorecity.sbn	1 KB	SBN File
the web		Baltimorecity.sbx	1 KB	SBX File
		Baltimorecity.shp	5 KB	SHP File
Other Places	*	Baltimorecity.shp	17 KB	XML Document
		Citieszip	17 KB	WinZip File
ESRIDATA		S County	3 KB	DBF File
My Documents		County	1 KB	SHX File
😡 My Computer		🖬 County.prj	1 KB	PRJ File
My Network Places		🖬 County.sbn	1 KB	SBN File
Grynnen		🖬 County.sbx	1 KB	SBX File
		County.shp	1 KB	SHP File
Details	*	McKeldinLib_staff	1 1/12	DBF File

KEY WORDS

There are two kinds of data that can be viewed in ArcGIS – vector and raster. Vector data is a format whereby points, lines, and polygons are used to represent real features on the earth's surface such as an address location, a street or a zip code area. Raster data is a continuous image of a portion of the earth's surface and is made up of grid cells or pixels as in an aerial or satellite image. If both vector data and raster data are georeferenced to the same position, they can be used in the same view.

2. After locating data, it is possible to preview it before adding it to ArcMap. Click once with the left mouse button on mdcounties.shp and then select the 'Preview' tab.


This will allow you to look at the mdcounties file. We will return to these files later.

Metadata

Metadata is loosely defined as "data about data." This is important, especially in a geospatial context, because it contains information about the source, author, creation, and geographic referencing. ArcCatalog allows you to view and manage metadata.

1. Click on the 'Description' tab.

This section provides a description of the files, spatial information, and a list of all of the attributes associated with the file.



Organization of ArcMap

ArcMap can be opened from multiple locations. This time, we will open it from ArcCatalog. It can also be opened from the start menu or an icon on the desktop.

Beginning with a Blank Project

1. From ArcCatalog, click on the ArcMap icon

Upon opening ArcMap you may see the following startup window:

ArcMap - Getting Started	using a template	<u>パメ</u> 目間日
Existing Maps Browse for more New Maps My Templates Templates Fandard Page Sizes Architectural Page S ISO (A) Page Sizes North American (AN Traditional Layouts Industry USA World Browse for more	My Templates	
	plication Data\ESRI\Desktop10.0\ArcMap\Templates\Normal.mo	
Default geodatabase for this may	: My Documents\ArcGIS\Default.gdb	What is this?
Lethornieurs and serringstore	ny populations per cats (per dair, gain	
Do not show this dialog in the	uture.	OK Cancel


This is a new feature with version 10 of ArcGIS software that allows you to make a shortcut to your most-used data location. Since we're just beginning, we are going to skip this option and simply use the default. Click on Cancel.

ArcMap makes a default geodatabase in the C:\My Documents\ArcGIS folder.

Now you will be in a new, blank document in ArcMap.

This area is known as the Map Display. This display area is where map features are drawn.

Menu Bar



When you begin, the menu bar changes to show the menu functions available. You can change the way the ArcMap looks by moving or hiding toolbars. Docking toolbars in another location can be done by clicking on the vertical gray bar at the left edge or top and dragging it to a new location.

To hide or show toolbars, click 'Customize' (on the menu bar) > 'Toolbars' and check or uncheck the name.


Any changes made to the interface will be kept and applied every time you use ArcMap. Please note that some toolbars are dependent upon the license level. Some toolbars and extensions will be visible, but the user will not be able to access the functionality if they do not possess the required license.

At this point, most of the icons of the button bar and tool bar are grayed out because we do not have any data in our view. Let's add data to see what functions are available to us.

Adding Data through ArcCatalog

There are two main ways to add data. We will begin with adding two data files – md_cities.shp and md_interst.shp – from ArcCatalog.

- 1. Click on the 'ArcCatalog' tab icon at the top right of the display. You will see the catalog tree.
- 2. Navigate to the data you want to add. For us, that is under Folder Connections C:\ESRI\GIS_WRKSHP
- 3. We will add two layers: md_interst and md_counties. Drag and drop it into the Table of Contents under Layers.




Adding Data through ArcMap

In addition to ArcCatalog, it is possible to add data directly through ArcMap.

- 1. Select the 'Add Data' button. If you selected the drop-down, choose the first option, Add Data. Or, from the menu bar, select 'File' > 'Add Data' > 'Add Data'.
- 2. Change directories until you find C:\ESRI\GIS_WRKSHP\
- 3. Select md_cities.shp and click the 'Add' button.

On the left-hand side of the view the three selected layers are displayed in the view's table of contents. Each layer has a little check mark in the box to its left. This means they are "turned on" and being displayed. If you uncheck them, that layer is no longer visible.



The colors of your layers and their order may differ from the example on the instructor's screen, but you should have all three datasets. Each of these layers contains geometric objects that represent some real world entity. Points are used in the md_cities layer to represent Maryland cities. (At a larger scale cities could be represented by polygons.) Lines are used in the md_interst layer to represent the interstate highways in Maryland, and polygons are used in the mdcounties layer to represent Maryland counties.


Notice how most of the button and tool bar functions are available to us now. Also notice the scale display next to the Add Data button. 1:2,922,847

This display tells you what the scale value is of the current view. If it displays the value '1: 2,922,847' that means that every one unit on the map is equal to 2,922,847 units in the real world. As you zoom in and out of the map the scale will change dynamically. Scale is an important concept in computer mapping. The scale of the map often determines the amount of information that can be shown without the map becoming too busy.

Also notice the position display at the bottom right of the screen. As you move the cursor around the view these units change dynamically according to your cursor's position. Your map units are likely in decimal degrees. -77.261 38.933 Decimal Degrees

Moving Around the Map Display

Now let's examine ways of zooming in and out and panning. The Tools toolbar contains eight buttons that provide zooming functions and allow you to define a custom view of the layer data. Some of the most useful ones are illustrated here.



Zoom In – zooms the view window in to a user-defined area. To use:

- 1. Select the Zoom In tool with the left mouse button. Notice the cursor changes to the magnifying glass with the + sign icon.
- 2. Go to one corner of the area you would like to zoom in on and click with the left mouse button. While holding down the mouse button, move the cursor to the opposite corner that defines the area you want to magnify.
- 3. Release the mouse and the view window should zoom in to your defined area and redraw.

Zoom Out – zooms the view window out from the point clicked. To use:

- 1. Select the Zoom Out tool with the left mouse button. Notice the cursor changes to the magnifying glass with the sign icon.
- 2. With the left mouse button click the area of the map you want to zoom out from. The view window should zoom out, centering on the area that you clicked.

Pan – moves all the view layer layers in the direction you move your mouse. It is a useful tool when viewing data that is larger than the view window, and you do not want to change your scale or loose detail by zooming out. To use:

- 1. Select the Pan tool with the left mouse button. Notice the cursor changes to a hand.
- 2. Click a spot on the view with the left mouse button, and while holding down the button move the mouse away from the direction you want to move the view and release the button. The view should move and redraw the view in the new location once the mouse button is released.

Full Extent – zooms the view window to the full extent of all layers shown in the view. This is very handy when you want to get back to the way things looked when you first added the layer.

Zoom to Previous Extent – zooms the view window back to the previous view window extent.

Practice using the zooming and panning tools to view the Maryland data. You may also zoom in and out by using the wheel on your mouse. You can always return to the initial view by pressing the 'Full Extent' button; so don't be afraid to move around!

0

Identifying Objects

Now let's examine the identify tool. This tool helps us to identify the objects of a layer. It is located on the Tools toolbar and it has the icon with the letter i in a blue circle. This tool will display the attributes of a particular layer object. These attributes are actually located in a table that we will discuss later.

To use the identify tool: 🤎

1. Click the identify tool with the left mouse button. Your cursor changes to a cross hair with the i icon.

When you click on a feature in the map, the Identify Results window will open and you can choose what layers you would like to be able to identify or see what you have identified.

Identify	the second s	×
Identify from:	<all layers=""></all>	•
md_cities Cumbe mdinterst 168 mdcountie Mlega	s	
-		×1
Location:	-78.753637 39.658284 Decimal Degrees	
Field	Value	
FID	0	
Shape	Point	
CITY_FIPS	21325	

SESSION 2 Setting Map Units, Display Units and Map Projection

One of the very first things that you should do after adding data is to set the map and display units. It is also a good idea to set the projection (if desired) at this stage as well. Setting these units will allow you to measure distances or compute areas. Display units should also be set if you are planning to create a map layout with a distance scale. To set the map and display units:

1. Right click on the data frame 'Layers' at the top of the legend and scroll down to 'Properties.'

	Labeling	•	additional bar Reference Scale:	I options for displaying coordinates in th	he status
	Reference Scale Advanced Drawing Options.	•	TID: See Cost	mai Degrees Helter > ArcMap Options > Data View L	
	Collapse All Layers		Units Map: Deci	nd Centres	-
86	Expand All Layers		Credks:		
	Select All Layers				-
	Turn All Layers Off		Description		
-	Turn All Layers On		Name: Lay	Dats Franie Coordinate System	Illumination Srid
	Paste Layer(s) Remove			Annotation Groups Extent Indicator	
🗏 🗹 mc 📑	Сору		Data Frame Proper	rtara	
-	New Basemap Layer				
• 💊 🗆 🗹 mc 📐	New Group Layer				
🖃 🗹 mc 梦	Add Data				

The 'Data Frame Properties' dialog box pops up. You should be in the 'General' tab. Take a look at the 'Units' portion of the dialog box. As you can see, the map units are already determined in this case, but you can choose what units you would like to use for display. The map units here are "decimal degrees" because all of the ESRI data is shipped in decimal degrees. Not all data is in decimal degrees. Some data, especially images, are in other map units such as meters.

1. Let's change our display units to "Miles".

Because our data is in decimal degrees, it is considered unprojected. We want to give our view a standard projection. For Maryland, the Maryland State Plane 1983 NAD projection is typically used. Let's set our data frame to this projection.

- **Data Frame Properties** ? × Feature Cache Annotation Groups Extent Indicators Frame Size and Position General Data Frame Coordinate System Illumination Grids Current coordinate system: GCS_North_American_1983 Datum: D_North_American_1983 14 Clear Transformations.. 21 1 Select a coordinate system E Favorites Modify... 🔚 Predefined 🕑 🧰 Layers Import... E 🗁 <custom> GCS_North_American_1983 New Add To Favorites 0K Cancel.
- 2. Click on the 'Coordinate System' tab.

Notice that it states that our current coordinate system is a geographic coordinate system, which is not projected.

Let's select a projected coordinate system.

- 3. Click on 'Predefined'.
- 4. Click on 'Projected Coordinate System'.
- 5. Scroll down and click on 'State Plane'.
- 6. Click on 'NAD 1983 (Feet)'.
- 7. Scroll down and choose 'NAD_1983_StatePlane_Maryland_FIPS_1900 (Feet)'.
- 8. Click 'Apply' and then 'OK'.

KEY WORDS	
preserves shape and maintains accurate dist states, but only at the expense of direction projections such as Mercator preserve direct and area. Depending on the use of your data others. Much of the data that you buy comm	Conformal Conic Projection. This projection ance in an east-west direction for the lower 48 (north, south, east and west) and area. Other tion and shape, but sacrifice accurate distance a, some projections may be more suitable than nercially is stored in decimal degrees, thereby s. However, data from governmental sources is
(geographic or projected). When you add ac systems, ArcMap creates an on-the-fly proj does not change the projection of the data is map display. On-the-fly projection works be system. If the coordinate systems are differe	it is shown based on its coordinate system dditional layers that have different coordinate ection and changes it to match the first. This itself, but rather the way it is displayed in the est of layers are based on the same coordinate nt, you will get a warning. You can display the ne differences are small, but if you need precise rdinate system transformation.
Warning:	
This coordinate system has a geographic coordinate system that differs from one or more data sources in the map.	
You may need to select different geographic transformations than the ones chosen for you in order to avoid alignment or accuracy problems with the data.	
Do you wish to use this coordinate system anyway?	
Yes No	

For more about map projections, consider this website: <u>http://egsc.usgs.gov/isb/pubs/MapProjections/projections.html</u>

Measuring in the Map Display

Now that we have set the map and display units, let's make some measurements. On the tools toolbar there is a button that allows you to measure elements of the layers. The measure tool is the button having the icon composed of a question mark within an arrow over the ruler.



- 1. Click the measure tool with the left mouse button. Your cursor changes to an L-shaped ruler with cross hairs and you get a pop-up window.
- 2. Move the cursor to the point on the map where you want to start measuring and click.
- 3. Now move the cursor to the point where you want to stop measuring and double-click.

Observe in the window the measurement you just made. This measurement is composed of a segment length and total length. It also indicates the display units of measurement. To change the units, click on the drop-down arrow next to the sum symbol.

Measure	×
~ - + Σ 💽 × 🔻	
Line measurement (Geodesic) Segment: 45.720753 Miles Length: 45.720753 Miles	

You can take measurements that are composed of multiple segments that do not follow a straight line. To do so:

- 1. Click the measure tool with the left mouse button.
- 2. Move the cursor to the point on the map where you want to start measuring and click <u>once</u>.
- 3. Now move the cursor to the next point along your defined path and click <u>once</u>. The first segment is defined.
- 4. Now move to the second point along your defined path and click once. The second segment is defined.
- 5. Repeat this process until you reach the point where you want to stop, and double-click.

Try measuring different parts of Maryland. What is the length of its border along the Mason-Dixon line? How wide is the Chesapeake Bay near Baltimore? What is the length from the Prince George's County side of Washington, DC to its opposite end in Montgomery County?

If you wish to measure in some other format (for example, kilometers instead of miles), you can also go back to the data frame > 'Properties > and change the display units.


SESSION 3

Symbology and Labeling

When a shapefile is opened in ArcGIS, symbols, styles and colors used to display the objects of a layer are randomly chosen. This symbology may not be (and usually is not!) the representation we wish to use for our map. We can modify the symbology so that our map is more presentable and readable. Let's start by changing the colors of the Maryland cities:

1. Click once, with the left mouse button, the dot below 'md_cities' in legend/ table of contents to bring up the Symbol Selector.

The "Symbol Selector" window opens.



The symbol selector has several features that allow you to edit each layer symbology regardless of type (i.e. point, line and polygon.) You can change the symbol, color, size, and angle as well as add more specific symbols to your list.

Let's change the styles and colors of our view layers. We'll begin with cities.

- 1. Click, with the left mouse button, on the shape 'Triangle 1.'
- 2. In the options box, click on the drop down box for color and choose a dark blue.
- 3. Change the size to 10.
- 4. Click 'OK'.

Repeat for the other two layers.

- 1. Click on the line under 'md_interst' layer name to edit the Maryland interstate layer.
- 2. Choose 'Highway'. Because this is already established as an accepted style, the color and size of the line will automatically be added.
- 3. Click 'OK'.
- 4. Click on the polygon under the 'mdcounties' layer name to edit the Maryland counties layer.
- 5. Select a neutral color like gray or beige.
- 6. Click 'OK' in the "Symbol Selector" window box to apply your changes.

Now we have a much more attractive view. You can experiment with different colors and patterns until you find the right ones to suit your final map.

SESSION 4

Saving ArcGIS Projects

As with most computer projects, it is a good idea to save your work. To do so:

- 1. Select 'File' > 'Save As' from the menu bar.
- 2. You will save all your work for this workshop to the GIS_TEMP folder on the desktop. Click on Desktop and double click on the GIS_TEMP folder, or navigate to it through the drop-down.
- 3. Type a name for your project in the Save dialog box that appears and press 'OK'.
- 4. Check to see that your file is where you expect to see it.

Note that your saved file has an .mxd extension. This stands for map document, and it is a GIS-specific file type. If you try to open this document without using GIS software, it won't work!

KEY WORDS

An ArcGIS project or map document is a file instructing ArcGIS on what data to use and how to display it. The data layers are not stored with the .mxd file. If you copy your project file to a disk you must also copy all of the dataset files used in your project to that disk as well or reset the location from the layer properties, source tab.

SESSION 5


Labeling: Dynamic labels

There are three types of labels available: dynamic, interactive, and annotation. Dynamic labels are created at once and operate as a group. ArcMap will adjust the label according to the scale so that the labels are visible. Although you can set rules for display, ArcMap decides where to place them. As a default, labels will not overlap. In addition, you cannot individually select or change them unless you convert them to annotation. This will be discussed later.

Before we label, it's important to set the rules and choose label position and priorities. Let begin with the 'md_cities' layer.

- 1. Right click on 'md_cities' to open the Context Menu. Many operations in ArcMap are performed through this menu.
- 2. Scroll down to 'Properties.' This opens the "Layer Properties" window.
- 3. Under the 'Labels' tab choose the 'Placement Properties' icon to open the "Placement Properties" window. The default priority location for labels is in the upper right corner. Let's change the location to the top center.

yer Properties					?!
General Source	Selection Display Symbology	Fields Definition Query	Labels Joins & Re	lates Time H	TML Popup
Label features	in this layer				
Method:	Label all the features the sam	e way.	<u>·</u>		
All features will b	e labeled using the options specifi	ed.			
Text String					
Label Field:	CITY_NAME		Expressio	n	
Text Symbol					
	AaBbYyZz	 Arial ■ - B Z U 	8 <u>▼</u> Symbol	1	
Other Options	~	Pre-del	fined Label Style		
1	nt Properties Scale	Range	Label Styles		
			ОК	Cancel	Apply



Initial point placement		<u>?</u> ×
Bottom Left Only	Left Center Only	Top Only, Prefer Right
0 0 1 0 2 0 0 2	2 1 2 0 0 0 0 0	0 0 2 0 1 0 0 2
Right Only, Prefer Top	Top Only, Prefer Center	Right Only, Prefer Center
Priority: 0 = Blocked, 1 =	Highest, 3 = Lowest	OK Cancel

- 4. Click on the 'Change Location' icon, with the left mouse button to open the "Initial point placement" window.
- 5. Scroll up and choose 'Top Only, Prefer Center.'
- 6. Press 'OK in this box as well as on the 'Placement Properties' box and 'Layer Properties' box.

Now that we have set the properties, let's label.

- 1. Right click on 'md_cities' to open the 'Context Menu' again.
- 2. Scroll down and click on 'Label Features.'

Let's also label the 'md_interst' as well.

- 1. Right click on 'mdinterst' to open the 'Context Menu' again.
- 2. Scroll down and click 'Label Features.'

Notice that some of the labels for md_cities have moved to make way for the new interstate labels.

It is possible to set your labels in a predefined style.

- 1. Right click on 'md_interst' to open the 'Context Menu' again.
- 2. Scroll down and click on 'Properties.'
- 3. Under the 'Labels' tab there should be an icon 'Label Styles' in the bottom right corner under the heading 'Pre-defined Label Style.' Click on the 'Label Styles' button.

lefined Label St
Label Styles

This brings you to the "Label Style Selector" window.

1. Choose the 'U.S. Interstate HWY' symbol in the upper right corner and click 'OK.'

Style Selector	The second s		
<u>[55]</u>		Preview	
U.S. Route	U.S. Interstate HWY	6	5
AaBbYyZz	AaBbYyZz	2.5	
Country 1	Country 2	Ŋ.	
AaBbYyZz	AaBbYyZz		
Country 3	Capital		
AaBbYyZz	AaBbYyZz		
County	Large City		
AaBbYyZz	Aa6 byyZz		
City	Town		
AaB bYyZz	AaBbYyZz	Prop	erties
Street	Physical Region	More	<u>S</u> tyles
AaBbYyZz	AaBbYyZz	Save	Reset
Historic Region	Coastal Region	ОК	Cancel

Unfortunately, the labels are too much all together.

- 1. We can set priority for viewing by right clicking on 'md_cities' > 'Properties' > 'Placement Properties.'
- 2. In the "Placement Properties" window click on the 'Conflict Detection' tab.

From here it is possible to define the priority of the labels. Labels for layers marked with a 'High' weight will be less likely to be overlapped by other layers. It, however, is not necessary in this case as dynamic labels are not flexible enough for our needs.

To be able to individually move labels we can convert the dynamic labels to annotation or use interactive labels.

Converting Dynamic Labels to Annotation

By converting dynamic labels to annotation we are able have all features labeled at once and also have the ability to move them individually. Let's convert the md_cities labels to annotation.

Close any extra dialog boxes if necessary. Right click on the 'md_cities' layer to 1. open the context menu.

- Scroll down to 'Convert Labels to Annotation'. 2.
- 3. If you get an overflow annotation dialog, just close it.

The 'Convert Labels to Annotation' dialog opens.

onvert Labels to Annotation		<u>?×</u>	The default option for storing
Store Annotation C In a database	Reference Scale 1:2,922,936		annotation is in a geodatabase. Because our data is not in a geodatabase, we will opt to store it
Create Annotation For			'In the map.'
All features C Features in	current extent C Selected features		1. Click the radial button 'In
Feature Layer	Annotation Group		the map.' 2. Click the 'Convert' button.
mdcities	mdcities Anno		
			Our labels are no longer dynamic and will no longer move according to scale, etc. Let's move some of our labels.
		-	
Destination: Annotation group stored i	in the map document		
Convert unplaced labels to unplace	d annotation Convert Can	cel	
		-	

- Click on the Select Elements tool. 1.
- k
- Click on a label. An aqua dotted line should surround the label. 2.
- As you put the cursor over the label it will turn into cross-hairs. Click and hold the mouse button, move the label, and then release the mouse button. 3.
- Double click on the label with the aqua line still surrounding it to access the 4. 'Properties' dialog. Here you can change the text, font, and symbology.

Labeling: Interactive Labels

Like annotation, interactive labels are graphics. Interactive labels can be added and moved individually from the 'Draw toolbar.' This allows you to place custom-created text on the map.



- 1. If necessary, use the menu bar to click on 'Customize' > 'Toolbars' > 'Draw' to display the Draw toolbar.
- 2. Click on the New Text button, which looks like an 'A'. When the cursor changes to a cross hairs with an 'A' click on the map and add text. This works for anywhere on the map.

There are 6 other options for the custom creation of text also available.

3. To access these, click on the drop down box (arrow pointing down) to the right of the 'New Text' button, which looks like an 'A.'



Once you use any of these tools to create a graphic object, little boxes or "handlebars" will appear around that object surrounded by an aqua colored line. That tells you that the object is selected. If an object is selected you can move the object to a different location with the Select Elements tool **N**. Click on the Select Elements tool, move it over the selected object, then press the left mouse button and drag the object to the new location. Once the object is moved to the location desired, you deselect the object by clicking anywhere in the view. The handlebars should disappear. You can reselect the object with the Select Elements tool by clicking on it with the left mouse button. The handlebars will reappear. If you want to delete an object just press the delete key with the object selected.

To use, select the appropriate tool with the left mouse button.

- To use the 'New text' and 'Label' tools you simply select the tool and click the spot on the view in which you want to place the text. A text window will appear allowing you to type in your text. Type the text and press 'OK.'
- To use the callout tool you must first click the point where the line pointer will begin. While holding down the mouse button, drag the pointer in the direction the text will appear. Release the button at the spot where the actual text will begin. A text window will appear allowing you to type in your text. Type the text and press 'OK.'
- To use the splined text tool click at the point where the text will begin. Use the tool to draw a line (does not have to be straight) by clicking at each segment point and double-clicking at the end. A text window will appear. Type the text and press 'OK.' The splined text tool is ideal for labeling text in a non-linear fashion such as along a river.
- To create new circle text, move to the spot on your view that will be the center of your circle. Click and hold down the mouse button while moving away from the circle's center until you reach your preferred radius. Release the mouse button at the radius position and add text. The text will fill a circular area.
- To create new rectangle text, move to the spot on your view that will define a corner of the rectangle. Click and hold down the left mouse button while moving to the opposite corner of the rectangle. Release the button at the opposite corner and add text. The text will fill the designated rectangle.
- To create new polygon text, move to the spot on your view that you want to begin your polygon and click with the left mouse button. Move the cursor to the endpoint of the first polygon side and click <u>once</u>. The first side is defined. Now move the cursor to the endpoint of the second side and click <u>once</u>. The second side is defined. Repeat this process until your polygon is complete, then <u>double-click</u> to end the polygon and add text.

Once a graphic object is drawn, it is possible to edit its features.

1. With the drawn object selected i.e. the "handlebars" displayed around the object, right click with the mouse.

慾	Zoon Whole Page	
덃	Zoon to Selected D	enents
\$	O/R	ChieX
Ø	Copy	Ctri+C
×	Delete	Delete
1	Convert To Graphic	
1d	0 mp	
iù.	Ungroup	
	Graphic Operations	
	Order	
	Nudge	,
	Align	
	Distribute	
	Rotate or Flip	,
6	Properties	

From this window you can also select other options that enable you to:

- Change the order of the graphics (send to front, back, etc.)
- Nudge the graphic up, down, to the left, or to the right.
- Align to the top, bottom, or other directions.
- Distribute horizontally or vertically; make the same size/height/width; or fit to margins.
- Change properties, including color, font, and font size.
- 2. To change properties, click on 'Properties' > 'Change Symbol.' This window will let you change color, font, and font size.

We won't need our labels at this time, so let's delete them. We can individually select them with the mouse button or we can do it all at once.

3. Click on 'Edit' on the menu bar > 'Select All Elements' and hit the delete button on your keyboard.

We have learned how to use some of the buttons and tools to view and edit our data. Now, let's begin to perform some analysis with our data.

SESSION 6

Performing Analysis in the Map Display

One way to perform analysis in ArcMap is to map certain attributes of layer data. For each element or object that composes a single layer there is a set of characteristics or attributes associated with that object. These attributes, also called fields, are stored in a table that is linked to the graphic object. Thus each object in our layer is associated with a record in the layer's attribute table. Let's view the attribute table for the mdcounties layer.

To open the attribute table:

1. Right click on 'mdcounties' to open the Context Menu. From the menu, click on 'Open Attribute Table.'

A table opens showing all the attributes stored with each of the Maryland County polygons.

FID	Shape	NAME *	STATE NAME	STATE FIPS	CNTY FIPS	FIPS	AREA	POP1990	POP1997	POP90 SOMI	HOUSEHOLDS	MALES	FEMALES	WHITE	BLAC
	olygon	Allegany	Maryland	24	001	24001	429.7112	74946	72727	174	29634	35274	39672	72955	15
	Polygon	Anne Arundel	Maryland	24	003	24003	419.3426	427239	470060	1019	149114	215082	212157	365953	5052
	Polygon	Baltimore	Maryland	24	005	24005	615.107	692134	720219	1125	268280	330339	361795	587898	854:
	Polygon	Calvert	Maryland	24	009	24009	220.3898	51372	68579	233	16986	25487	25885	42825	80-
4 F	Polygon	Caroline	Maryland	24	011	24011	326.0527	27035	29424	83	9983	13115	13920	22355	44:
5 F	olygon	Carroll	Maryland	24	013	24013	452.3964	123372	146120	273	42248	60749	62623	119336	29
	olygon	Cecil	Maryland	24	015	24015	356.6436	71347	80374	200	24725	35622	35725	67450	32
7 F	olygon	Charles	Maryland	24	017	24017	469.1563	101154	115000	216	32950	50249	50905	80234	184
8 F	olygon	Dorchester	Maryland	24	019	24019	584.1176	30236	29953	52	12117	14324	15912	21548	84
9 F	Polygon	Frederick	Maryland	24	021	24021	667.3302	150208	182694	225	52570	73955	76253	139909	80
10 F	Polygon	Garrett	Maryland	24	023	24023	656.0226	28138	29516	43	10110	13721	14417	27963	1
11 F	olygon	Harford	Maryland	24	025	24025	450.1069	182132	212090	405	63193	90936	91196	162559	155
12 F	olygon	Howard	Maryland	24	027	24027	253.5448	187328	228794	739	68337	93252	94076	155899	220
13 F	olygon	Kent	Maryland	24	029	24029	295.8979	17842	18980	60	6702	8629	9213	14085	35
14 F	Polygon	Montgomery	Maryland	24	031	24031	506.197	757027	823804	1496	282228	364880	392147	580635	922
15 F	Polygon	Prince Georges	Maryland	24	033	24033	499.2607	729268	778730	1461	258011	353423	375845	314616	3697
16 F	olygon	Queen Annes	Maryland	24	035	24035	372.9558	33953	38564	91	12489	16789	17164	29911	38
17 F	olygon	St. Marys	Maryland	24	037	24037	363.9711	75974	83473	209	25500	38674	37300	64129	102
18 F	olygon	Somerset	Maryland	24	039	24039	313.8686	23440	24251	75	7977	12424	11016	14282	89
19 F	olygon	Talbot	Maryland	24	041	24041	276.2065	30549	32565	111	12677	14491	16058	24833	55
20 F	olygon	Washington	Maryland	24	043	24043	467.5442	121393	127669	260	44762	61275	60118	112828	72
21 F	olygon	Wicomico	Maryland	24	045	24045	384.322	74339	79716	193	27772	35614	38725	56755	165
	1	har r	he i y	1~·	10.47	0.017	1 470 0005	05000				10051		07050	•

Let's just briefly examine the attributes in the layer table window:

2. Move the mouse to the scroll bar at the bottom of the table. Using the left mouse button click the scroll arrow to the right to view more attributes.

One of the first fields is "Name" which is the name of the county. Other attributes stored for each county include "Area," "Pop90," "Males," Females," "White," "Black," "Married," "Medianrent," and so on. Much of this data is Census data and includes numerical data that we can use in our analysis. Notice at the bottom it says "Records (0 of 24 Selected)." It's tells us we have a total of 24 items in our table. There are 23 counties in Maryland plus Baltimore City.



- 3. Move the mouse to the top of the table. Right click on the 'Name' field. It should open a window:
- 4. Click, with the left mouse button, the sort ascending or the sort descending options on the button bar.

Notice how the names of the counties will sort themselves according to alphabetical order. When ascending, it will sort from A-Z or 0-9, when descending it will sort from Z-A or 9-0. Try it with the other columns, preferably those with integers. Such a quick organization of data is beneficial in understanding the range of data.

Other options to summarize, calculate values, freeze/unfreeze a column, and delete a field are also in this window.

Options for selecting and querying data are also possible from the attribute table. These will be discussed later in the workbook.

Mapping by Category: Unique Values

It is possible to assign different colors according to values in the attribute table. Let's make every county in Maryland a different color.

- 1. Hide the 'md_cities' and the 'md_interst' layers by unchecking the boxes next to their names.
- 2. Right click on 'mdcounties' > 'Properties.'
- 3. Click on the 'Symbology' tab once with the left mouse button.

F	Draw ca	tego	ries using	g unique v	alues of one fie	eld. 📘		Import
Features	⊤ ⊢Value Fie	-		· ·				
Categories Unique values				7		np		
	CNTY_F	IPS		/			•	
- Unique values, many (
End of the symbols in a Quantities	Symbol	Valu	e		Label		Count	
Charts		kall o	her value:	>	kall other values:	>	0	
Multiple Attributes	<u> </u>	<he< td=""><td>ding></td><td></td><td>CNTY_FIPS</td><td></td><td>24</td><td></td></he<>	ding>		CNTY_FIPS		24	
Multiple Attributes		001	_		001		1	
		003			003		1	
		005			005		1	
		009			009		1	
		011			011		1	
MR P PA		013			013		1	
and a		015			015		1	
K. S.		017			017		1	
1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1		019			019		1	-
Y VY	Add All V	alues	Add V	alues	Remove	Remove All	Ad	lva <u>n</u> ced

4. On the left side click on 'Categories' and then click on

'Unique values.'

5. Choose 'CNTY_FIPS' in the drop down box under 'Value Field.'

6. Click on the 'Add All Values' button (bottom left) 7. Choose any color ramp in the drop down box in the top right side.

If you want to control the colors assigned to each county, double click on the colored symbol. It will allow you to change the color.


8. Click the 'OK' button.

Each county will be given a different color. This is useful for distinguishing differences based on attributes.

Mapping by Quantity: Color Maps

Now let's perform some analysis using a common mapping technique called color or choropleth maps. These maps are ideal for showing all sorts of data including both numerical and descriptive text. We will use the Maryland county layer again for our analysis:

- 1. Right click on 'mdcounties' > 'Properties'.
- 2. Click on the 'Symbology' tab once with the left mouse button. This takes us again to the section of Layer Properties that allows us to change symbols.
- 3. This time, click on 'Quantities' in the window on the left and choose 'Graduated colors'.
- 4. Under the section for 'Fields' choose 'Females' in the drop down box and click 'OK'.



The map changes to display the counties according to the number of females:

In the example, the lighter colors represent counties where the number of females is low (relatively speaking) such as western Maryland or the Eastern Shore. The colors darker represent areas where the female population is high -Baltimore City.

Montgomery County and Prince George's County. Try this again, with Pop1990 and see if it the results with females are the same as the population in general.

Let's look at the 'Layer Properties' more closely to examine other ways to portray this data.

- 1. Right click on 'mdcounties' > 'Properties' again to bring up Layer Properties. It should automatically come up in symbology mode. If not, check the 'symbology' tab.
- 2. Look in the Classification area of the window in the upper right corner. It identifies that we are classifying by natural breaks and have 5 classes.
- 3. Click on the 'Classify' button.

The "Classification" window will appear:

Classification			? ×
Classification		Classification Statistics	10 10 m
Method: Natural Breaks (Jenk Classes: 5	s) 💌	Count: Minimum: Maximum:	24 9213 392501
Data Exclusion Exclusion	Sampling	Sum: Mean: Median: Standard Deviation:	2462797 102617 39199 131267
Columns: 100 🛨 🛛 🗆 Sh	ow Std. Dev. 🔲 Show Mean	1	
4T88957 3-	212157	332501	Break Values × 25885 50905 94076 212157 392501 392501
2-			
1-1-1		11	
9213 105035	200857 2	96679 392501	ОК
📕 Snap breaks to data values			Cancel


The "Classification Statistics" window in the upper right corner provides useful statistics that may help in our analysis such as the minimum value, maximum value, mean and standard deviation. The chart at the bottom shows you where the breaks will occur. You change these manually by clicking on a line with the left mouse button, holding it, moving it to the new area, and releasing it.

Now let's reclassify the same data to portray a different view:

The Classification section in the upper left allows you multiple ways to classify the data. You can choose the type of classification, number of classes and a rounding value. Let's try a different classification scheme.

- 1. From the 'Method' drop-down box select "Equal Interval" and from the 'Number of classes' drop-down box select "4."
- 2. Click OK to close the Classification window.
- 3. Click 'OK' on the Layer Properties window to change the map.

The view is now changed to display four colors representing the four classes:



The new classification changes the groupings of our color map resulting in fewer categories and differences in which categories the counties fall into. Experiment with the different classification systems to see their effect on the data.

KEY WORDS

The classification options are defined (by ESRI) below. Some of the methods are not suitable for certain types of data.

- Natural Breaks This is the default classification method in GIS. This method identifies breakpoints between classes using a statistical formula (Jenk's optimization). Natural Breaks finds groupings and patterns inherent in your data.
- Quantile In the quantile classification method, each class contains the same number of features.
- Equal Interval The equal interval method divides the range of attribute values into equal sized sub-ranges. The features are classified based on those sub-ranges.
- Standard Deviations ArcGIS finds the mean value and then places class breaks above and below the mean at intervals of either 1/4, 1/2, or 1 standard deviations until all the data values are contained within the classes.
- Manual and Defined Interval ArcGIS allows you to set your own classification methods.

Mapping by Quantity: Dot Maps

Let's analyze a different attribute using another type of map – the dot or dot density map. It is ideal for mapping numerical data.

Features	Draw quantities using dots to show values.	Import
reatures Categories	Field Selection	/ <u></u>
Quantities Graduated colors Graduated symbols Proportional symbols Dot density Charts Multiple Attributes	MARHH CHD MARHH CHD MARHH CHLD FHL CHLD HSE UNITS VACANT OWNER OCC RENTER OCC MEDIAN VAL	<u>↑</u>
	Densities Min Mean Max Dot Size Background Background Background Discussion Densities Min Mean Max	Properties.

 Right click on 'mdcounties' > 'Properties' again to bring up Layer Properties. It should


> automatically come up in symbology mode. If not, click the 'symbology' tab.

- 2. Click on 'Quantities' and then 'Dot density.'
- 3. Under the 'Field Selection' list click on 'Vacant.'
- 4. Click on the right arrow button to add it to the box on the right.

Notice that the Dot Value comes up as 300.

5. Click 'OK.'

The following dot density map appears:



Notice how the number of vacant housing differs dramatically between counties. Some counties, like Baltimore City have a lot of vacant housing. Others, like Calvert County, have very few. The dots do not represent the actual location of vacant homes. They are randomly placed in each county. Remember that each dot represents 300 vacant homes, not a single vacant house, so some generalization occurs.

Chart Maps

This third type of analysis overlays a chart onto our map. It is a good mapping technique when you want to display and compare multiple values or values for each layer object. In our chart map we will examine the number of homeowners vs. renters.

- Right click on 'mdcounties' > 'Properties' again to bring up Layer Properties.
- 2. Click on 'Charts' and then 'Pie.'
- 3. From the 'Field Selection' list on the left-hand side scroll down until you find "Owner_occ" and "Renter_occ."

how: Features	 Draw pie chart for each feature. 	Import
Categories	Field Selection	
Quantities	FHH_CHILD	
Charts		
Pie	VACANT > OWNER_OCC	
Bar/Column	MEDIAN VAL RENTER_OCC	T
Stacked	UNITS_1DET	- 1
Multiple Attributes	UNITS_1ATT	+
	UNITS2	
	UNITS3_9	
	Background: Color Scheme:	-
u de		
	Prevent chart overlap	
	Properties Exclusion Size	
M.		

- 4. Select both fields (by holding down the Ctrl button while clicking) then click the right arrow button.
- 5. Click 'OK.'

If your pie charts are too large:

- 6. Re-open the Layer Properties.
- 7. In the Symbology tab, click on the 'Size' button and change the symbol size to "20."
- 8. Click 'OK' twice to close the open windows.

Our view changes to a chart map depicting the breakdown in renter versus owner occupied housing in Maryland. Which county appears to have the most renters in the state? Which county appears to have the most owners? Can you see any spatial patterns in homeownership?

Let's change our map back to Single Symbol.

- Right click on 'mdcounties' > 'Properties' again to bring up Layer Properties.
 Click on 'Features.' This will remove all symbology.
 Change the color, if desired, by clicking on the 'Symbol' box.

- 4. Click 'OK' to close the window.

Layer Properties	
Contraction of the second s	tion Display Symbology Fields Definition Query Labels Joins & Relates
Show: Features Single symbol Categories Quantities Charts Multiple Attributes	Draw all features using the same symbol. Import Symbol Advanced +
V C B - P J Z	Label appearing next to the symbol in table of contacts:
	Additional description appearing next to the symbol in your map's legend

SESSION 7

Queries

The real power of GIS lies in the queries that can be performed on the data. Through queries we can find precise information quickly. We can also ascertain patterns in the data such as the location of customers or low-income residents.

Attribute Queries

There are two main ways to create attribute queries. The first way is through the menu bar.

1. Click on 'Selection' and then 'Select by Attribute' to open the Select by Attributes window.

Select F	By Atti	ributes		? ×
Layer:	R	Independence medication → medication medicati medication medication medication medic	ities ow selectable layers in this list	•
Method:	C	ireate a ne	ew selection	•
	E_NAM E_FIPS' _FIPS''			×
=	\leftrightarrow	Like	'Howard'	^
>	> =	And	(Kent' 'Montgomery'	
<	< =	Or	'Prince Georges' 'Queen Annes' 'Somerset'	
_ %	0	Not	St. Marys'	~
ls			Get Unique Values Go To:	
SELECT	* FROM	1 mdcour	ities WHERE:	
"NAME	'' = 'Prin	ce Georg	es'	2
Clea	IT I	Verify	Help Load	ave
			OK Apply I	Close


The query window lets you choose which layer you would like to select from and changes the list of layer attributes below depending on what you pick in the drop down box. It also contains a set of operational tools in the middle left and all the table values for each attribute on the middle right. The operational tools including the standard mathematical ones =, >, <, etc. as

well as the Boolean operators and, or and not. You build a query by first selecting an attribute and then an operation you wish to perform with its values.

Let's start with a very simple query that locates an object:

- 2. Change the 'Layer' list drop down box to 'mdcounties.'
- 3. Under 'Method' choose 'Create a new selection.'
- 4. Double-click the attribute "Name."
- 5. Then single click the "=" sign operation.
- 6. Click on the 'Get Unique Values' button. A list of attributes will appear in the box on the right.
- 7. Finally, in the box listing the attributes, scroll down until you find the name "Prince George's" and double-click the name. Each time you click or double-click the name or symbol should appear in the query builder box below.
- 8. Verify that your query looks the same as the example box on the previous page and click 'OK.'

The boundary of Prince George's County is highlighted in the aqua. ArcMap always highlights selected objects in aqua as a default, which is why it is good to have a gray or darker background for queries.



SESSION 8

Creating a New Map Layer

Now that Prince George's County has been selected it can be exported from the map and added as its own layer. To do this:

- 1. Right click on 'mdcounties' to open the context menu.
- 2. Scroll down to 'Data' > 'Export Data'. This opens the "Export Data" window.
- 3. Within this window choose to export "selected features" and use the same coordinate system as the "data frame".
- 4. Save the file in the appropriate folder (GIS_TEMP on the desktop) and give it a meaningful name.
- 5. Click 'OK" and you will then be asked if you wish to add the exported data to the map as a layer. If you choose 'yes' Prince George's County will appear in the map as a new layer.

Export Data 🔹 💽 🔀	
Furgetty Collected features	
Export: Selected feature	
Use the same coordinate system as:	
C this layer's source data	
 the data frame 	
 the feature dataset you export the data into (only applies if you export to a feature dataset in a geodatabase) 	
Output shapefile or feature class:	
C:\Documents and Settings\Desktop\GIS_TEMP\P	ty.shp
OK Cancel	

Check that your file appears in the folder you designated.

Spatial Queries

We examined simple queries about location and character using attribute data. Now let's look at queries that consider the spatial relationship between objects or layers. This is where the true power of a GIS is demonstrated.

Perhaps we want to locate all of the cities within Prince George's County so that we may export them as a new layer file as well.


1. From the menu bar select 'Selection' > 'Select by Location'.

The "Select By Location" window opens.

	m one or more layers based on where they ar	re
located in relation to the fea I want to:	itures in another layer.	
select features from		-
the following layer(s):		-
✓ macries		
mdcounties		
	ers in this list	
	ers in this list	
	ers in this list	
that: are completely within	ers in this list	•
 Only show selectable lay that: are completely within the features in this layer: PGCounty 	ers in this list	•
hat: are completely within the features in this layer:		•
that: are completely within the features in this layer: PGCounty Use selected features	(0 features selected)	•
that: are completely within the features in this layer: PGCounty Use selected features Apply a buffer to the fea	(0 features selected)	•
that: are completely within the features in this layer: PGCounty Use selected features	(0 features selected)	•
that: are completely within the features in this layer: PGCounty Use selected features Apply a buffer to the fea	(0 features selected) itures in PGCounty	•

- 2. From the first drop-down box labeled 'I want to:' choose the option "select features from."
- 3. Check the box "md_cities" under the option 'the following layer(s).'

- 4. In the next two drop down boxes choose "are completely within" and then "PGCounty."
- 5. Click the 'Apply' button.



All of the Maryland cities (in this dataset) that are within Prince George's County are selected. Now try exporting the selected cities as a new map layer. See the previous section for instructions.

SESSION 9

Layouts

Layouts are a way of allowing you to make professional quality presentations. You can also include tables and charts in a layout as well. To make the transition from view to layout easier, you should remember to do a few things while in the Map Display:

- Set the map and display units first. This needs to be done before a scale is placed on the layout. (Right click on Layers > Properties > General tab)
- Choose appropriate colors for your map. Otherwise you will have to return to your map to make changes.
- Give your view and layers meaningful names. These will be the names the layout uses to title your map and label the legend.
 - 1. Clear all of your selected objects.
 - 2. Make sure that your layers have appropriate colors.
 - 3. Make sure that the map and display units are set.
 - 4. Label any features on the map that you want labeled on your layout.
 - 5. Provide meaningful names to the layers.

	Selection Display Symbology Fields Definition Query Labels Joins & Relates	
Layer Name:	Prince George's County 🔽 Visible	
Description:		
Credits:		
	y the range of scales at which this layer will be shown: er at all scales	
C Don't sho	w layer when zoomed:	
Out beyo	nd: <none> (minimum scale)</none>	
	nd: <none> (maximum scale)</none>	

To do so:


- 1. Right click on 'PGCounty' > 'Properties'
- 2. Click on the 'General' tab.
- 3. Under 'Layer Name:' change it to read "Prince George's County"
- 4. Click OK.

Repeat this process with the PG Cities layer. An alternate method for changing the name of a layer is to click on it once, then pause and click on it again. You'll see an editable box.

Now we are ready for layout.

1. From the main menu, click 'View' > 'Layout View.' You must be in layout view to add legend items to your map.

The view of our map is now visible as a layout. Notice that the layout toolbar is now visible.



From here it is possible to zoom in, zoom out, pan, fixed zoom in, fixed zoom out, zoom to whole page, zoom to 100%, go back and forward between extents, and change the percentage of your zooming. Practice using these tools.

Insert		Selection	Geop
9	Data Frame		
<u>Title</u>	Title		
A	Text		
	Dy	mamic Text	•
	Ne	atline	
1111	Le	gend	
* N	North Arrow		
2	Scale Bar		
<u>1:n</u>	Scale Text		
	Pic	ture	
	Ob	oject	

Adding a Title, Scale Bar, North Arrow, and Legend

- 1. From the menu bar, click on 'Insert'. This box allows you to add various elements to the layout.
- 2. Click on 'Title' and a little box will appear on the layout with the name you chose when you saved your project. It is possible to change the name by clicking on the box and typing in new text.
- 3. Add the North Arrow and Scale bar by clicking on those options from the menu bar. For each of these you will be given a range of choices.
- 4. Pick the one that looks best to you and click 'OK'.

For the legend we will be using the Legend Wizard. It opens by asking you what layers you want in the legend.

- 1. From the top menu, choose Insert > Legend.
- 2. Only choose the new layers you added to the map yourself, PG County and PG Cities. Remove the other layers by highlighting them and clicking on . The two layers you want in your legend should appear in the "Legend Items" area on the right.
- 3. The next box allows us to decide properties for our legend title. The default options are good, except we would like to have our legend centered. Under 'Title Justification' choose the option to center and click 'Next'.
- 4. The next box deals with the legend frame. At the top drop down box, choose any type of border and click 'Next'.
- 5. We will go with the default in the next two boxes for the symbol patch and spacing. Click 'Next' twice.

From here we have most of the elements but they are not in the right place.

SESSION 10

Moving Graphics and Layout Objects

To move a graphic object:

- 1. Select it with the Select Elements tool so that its "handlebars" appear.
- k
- 2. The cursor will change to an arrow cross when placed over the graphic. Simply click and drag the object to its new location and release the mouse button. You can select multiple objects to move at once by holding down the shift key when selecting the objects.

Enlarging and Reducing Graphic Object Size

To enlarge or reduce the size of a graphic object:

- 1. Select the object so that the "handlebars" appear.
- 2. Move the cursor so that it is over one of the handlebar squares until it changes to a double arrow.
- 3. Click and drag the handle bar square away from the graphic's center to enlarge. Drag the handle bar square into the graphic's center to reduce.
- 4. Release the cursor when the graphic is at the appropriate size.



Grouping and Ungrouping Graphic Objects

To group multiple objects together as one:

- 1. Select each object while holding down the Ctrl key.
- 2. Right click anywhere on the layout and choose 🔀 Group To ungroup objects select the consolidated object, right click anywhere on the layout and choose 'Ungroup'.

SESSION 11

Adding Text and More Graphics

Add additional text and graphic objects using the draw toolbar just as you would in the Map Display or from the 'Insert' menu. Let's add a text box for source as well as author/date.

1. From the menu bar, click on 'Insert' > 'Text'. In one box type "Source: ESRI Data & Maps 2001". In the other type your name and the date.

Toggling Back and Forth (Layout View/Data View)

It is possible to go back and forth between the Map Display and the layout view by using the buttons located at the bottom left of the view window.

Printing/Exporting the Layout

- 1. Once your layout is finished you can print it by pressing the print button or from the menu bar select 'File' > 'Print'.
- 2. When the print window opens press 'OK.'

It is also possible to save the layout in a variety of file types.

1. From the menu bar select 'File' > 'Export Map'.

From here you can choose the location to save it, alter the resolution, and select a file type.

EMF (*.emf)
EPS (".eps)
Al (".ai)
PDF (".pdf)
SVG (*.svg)
BMP (".bmp)
JPEG (*.jpg)
PNG (".png)
TIFF (".tif)
GIF (".gif)